

## ***Programming Guide*** ***GTM-521XFX2***

3D TouchPrint® *Optical Fingerprint Recognition* **EMBEDDED** Module

**Version 1.0**

**Jun 19 , 2017**

GINGY TECHNOLOGY INC.  
No.1, Lixing 1st RD,  
Science Park, HsinChu,  
30077,Taiwan,R.O.C.  
TEL: 03-563-2500  
<http://www.gingytech.com.tw>

## Table of Contents

Revision History .....	4
1. General Description .....	5
<b>1.1. About this document</b> .....	5
<b>1.2. Related documents</b> .....	5
2. Protocol: Packet Structure .....	6
<b>Command Packet (Command)</b> .....	6
<b>Response Packet (Acknowledge)</b> .....	6
<b>Data Packet (Data)</b> .....	7
3. Protocol: Commands Summary .....	8
4. Protocol: Error Codes .....	10
5. Protocol: Command Details .....	12
<b>5.1. Initialization(<i>Open</i>)</b> .....	12
<b>5.2. Termination(<i>Close</i>)</b> .....	14
<b>5.3. Fast searching of the device(<i>UsbInternalCheck</i>)</b> .....	14
<b>5.4. CMOS LED control(<i>CmosLed</i>)</b> .....	15
<b>5.5. Changing UART baud rate (<i>ChangeBaudrate</i>)</b> .....	16
<b>5.6. Get enrolled fingerprint count(<i>GetEnrollCount</i>)</b> .....	17
<b>5.7. Check enrollment status(<i>CheckEnrolled</i>)</b> .....	17
<b>5.8. Start an enrollment(<i>EnrollStart</i>)</b> .....	18
<b>5.9. Make 1<sup>st</sup> template for an enrollment(<i>Enroll1</i>)</b> .....	18
<b>5.10. Make 2<sup>nd</sup> template for an enrollment(<i>Enroll2</i>)</b> .....	19
<b>5.11. Make 3<sup>rd</sup> template for an enrollment, merge three templates(<i>Enroll3</i>)</b> .....	20
<b>5.12. Check finger pressing status(<i>IsPressFinger</i>)</b> .....	21
<b>5.13. Delete one fingerprint(<i>DeleteID</i>)</b> .....	22
<b>5.14. Delete all fingerprints(<i>DeleteAll</i>)</b> .....	22
<b>5.15. 1:1 Verification(<i>Verify</i>)</b> .....	23
<b>5.16. 1:N Identification(<i>Identify</i>)</b> .....	23
<b>5.17. 1:1 Verification of Template(<i>VerifyTemplate</i>)</b> .....	24
<b>5.18. 1:N Identification of Template(<i>IdentifyTemplate</i>)</b> .....	25
<b>5.19. Capture fingerprint(<i>CaptureFinger</i>)</b> .....	26
<b>5.20. Make Template(<i>MakeTemplate</i>)</b> .....	27
<b>5.21. Get fingerprint image(<i>GetImage</i>)</b> .....	28
<b>5.22. Get raw image(<i>GetRawImage</i>)</b> .....	29
<b>5.23. Get template(<i>GetTemplate</i>)</b> .....	29
<b>5.24. Set template(<i>SetTemplate</i>)</b> .....	30
<b>5.25. Start database download, obsolete(<i>GetDatabaseStart</i>)</b> .....	30
<b>5.26. End database download, obsolete(<i>GetDatabaseEnd</i>)</b> .....	31

5.27.	<b>Set SecurityLevel</b>	32
5.28.	<b>GetSecurityLevel</b>	32
5.29.	<b>EnterStandbyMode</b>	33
5.30.	<b>Identify_Template2</b>	34
6.	Protocol: Flowchart, description	35
6.1.	<b>Capture of the fingerprint image</b>	35
6.2.	<b>Identifying and Verifying</b>	35
6.3.	<b>Enrollment</b>	35

## Revision History

[illegible]

## 1. General Description

### 1.1. *About this document*

The document is created to facilitate the firmware porting for the embedded system.

### 1.2. *Related documents*

You can find relative datasheets, include:

GTM-521XFX2 datasheet

GTM-521X FX2 programming guide

GTM-521X FX2 SDK

## 2. Protocol: Packet Structure

(Multi-byte item is represented as Little Endian.)

### *Command Packet (Command)*

OFFSET	ITEM	TYPE	DESCRIPTION
0	0x55	BYTE	Command start code1
1	0xAA	BYTE	Command start code2
2	<i>Device ID</i>	WORD	Device ID: default is 0x0001, always fixed
4	<i>Parameter</i>	DWORD	Input parameter
8	<i>Command</i>	WORD	Command code
10	<i>Check Sum</i>	WORD	Check Sum (byte addition) OFFSET[0]+...+OFFSET[9]= <i>Check Sum</i>

### *Response Packet (Acknowledge)*

OFFSET	ITEM	TYPE	DESCRIPTION
0	0x55	BYTE	Response start code1
1	0xAA	BYTE	Response start code2
2	<i>Device ID</i>	WORD	Device ID: default is 0x0001, always fixed
4	<i>Parameter</i>	DWORD	<b>Response == 0x30:</b> (ACK) Output Parameter <b>Response == 0x31:</b> (NACK) Error code
8	<i>Response</i>	WORD	<b>0x30:</b> Acknowledge (ACK). <b>0x31:</b> Non-acknowledge (NACK).
10	<i>Check Sum</i>	WORD	Check Sum (byte addition) OFFSET[0]+...+OFFSET[9]= <i>Check Sum</i>

## *Data Packet (Data)*

OFFSET	ITEM	TYPE	DESCRIPTION
0	0x5A	BYTE	Data start code1
1	0xA5	BYTE	Data start code2
2	<i>Device ID</i>	WORD	Device ID: default is 0x0001, always fixed
4	<i>Data</i>	N BYTES	N bytes Data The size is pre-defined per protocol stage
4+N	<i>Check Sum</i>	WORD	Check Sum (byte addition) $OFFSET[0] + \dots + OFFSET[4+N-1] = \textit{Check Sum}$

### 3. Protocol: Commands Summary

In a command packet *Command* can be one of below.

Number (HEX)	Alias	Description
01	<i>Open</i>	Initialization
02	<i>Close</i>	Termination
03	<i>UsbInternalCheck</i>	Check if the connected USB device is valid
04	<i>ChangeBaudrate</i>	Change UART baud rate
12	<i>CmosLed</i>	Control CMOS LED
20	<i>GetEnrollCount</i>	Get enrolled fingerprint count
21	<i>CheckEnrolled</i>	Check whether the specified ID is already enrolled
22	<i>EnrollStart</i>	Start an enrollment
23	<i>Enroll1</i>	Make 1 <sup>st</sup> template for an enrollment
24	<i>Enroll2</i>	Make 2 <sup>nd</sup> template for an enrollment
25	<i>Enroll3</i>	Make 3 <sup>rd</sup> template for an enrollment, merge three templates into one template, save merged template to the database
26	<i>IsPressFinger</i>	Check if a finger is placed on the sensor
40	<i>DeleteID</i>	Delete the fingerprint with the specified ID
41	<i>DeleteAll</i>	Delete all fingerprints from the database
50	<i>Verify</i>	1:1 Verification of the capture fingerprint image with the specified ID
51	<i>Identify</i>	1:N Identification of the capture fingerprint image with the database
52	<i>VerifyTemplate</i>	1:1 Verification of a fingerprint template with the specified ID
53	<i>IdentifyTemplate</i>	1:N Identification of a fingerprint template with the database
60	<i>CaptureFinger</i>	Capture a fingerprint image(256x256) from the sensor
61	<i>MakeTemplate</i>	Make template for transmission
62	<i>GetImage</i>	Download the captured fingerprint image(256x256)
63	<i>GetRawImage</i>	Capture & Download raw fingerprint image(320x240)
70	<i>GetTemplate</i>	Download the template of the specified ID
71	<i>SetTemplate</i>	Upload the template of the specified ID
72	<i>GetDatabaseStart</i>	Start database download, <b>obsolete</b>



Number (HEX)	Alias	Description
73	<i>GetDatabaseEnd</i>	End database download, <b>obsolete</b>
F0	<i>SetSecurityLevel</i>	Set Security Level
F1	<i>GetSecurityLevel</i>	Get Security Level
F4	<i>Identify_Template2</i>	Identify of the capture fingerprint image with the specified template
F9	<i>EnterStandbyMode</i>	Enter Standby Mode (Low power mode)
30	<i>Ack</i>	Acknowledge.
31	<i>Nack</i>	Non-acknowledge.

## 4. Protocol: Error Codes


When response packet is Non-acknowledge, *Parameter* represents an error code as below.

NACK Parameter	Value	Description
NACK_TIMEOUT	0x1001	<b>Obsolete</b> , capture timeout
NACK_INVALID_BAUDRATE	0x1002	<b>Obsolete</b> , Invalid serial baud rate
NACK_INVALID_POS	0x1003	The specified ID is not between 0~Max
NACK_IS_NOT_USED	0x1004	The specified ID is not used
NACK_IS_ALREADY_USED	0x1005	The specified ID is already used
NACK_COMM_ERR	0x1006	Communication Error
NACK_VERIFY_FAILED	0x1007	1:1 Verification Failure
NACK_IDENTIFY_FAILED	0x1008	1:N Identification Failure
NACK_DB_IS_FULL	0x1009	The database is full
NACK_DB_IS_EMPTY	0x100A	The database is empty
NACK_TURN_ERR	0x100B	<b>Obsolete</b> , Invalid order of the enrollment (The order was not as: <b>EnrollStart -&gt; Enroll1 -&gt; Enroll2 -&gt; Enroll3</b> )
NACK_BAD_FINGER	0x100C	Too bad fingerprint
NACK_ENROLL_FAILED	0x100D	Enrollment Failure
NACK_IS_NOT_SUPPORTED	0x100E	The specified command is not supported
NACK_DEV_ERR	0x100F	Device Error, especially if Crypto-Chip is trouble
NACK_CAPTURE_CANCELED	0x1010	<b>Obsolete</b> , The capturing is canceled
NACK_INVALID_PARAM	0x1011	Invalid parameter
NACK_FINGER_IS_NOT_PRESSED	0x1012	Finger is not pressed
NACK_RAM_ERROR	0x1013	Memory setting fail

NACK_TEMPLATE_CAPACITY_FULL	0x1014	Template capacity is full
NACK_COMMAND_NO_SUPPORT	0x1015	Function no support
Duplicated ID	0 – Max	There is duplicated fingerprint (while enrollment or setting template), This error describes just duplicated ID

## 5. Protocol: Command Details

### 5.1. Initialization(*Open*)



*Open* command is used to initialize the device; especially it gets device's static info.

**NOTE:**


After the finger module is powered on, Must be wait 100ms and then send the *OPEN* command.

## Description of *devinfo* structure

Field	Sample	Description
<i>FirmwareVersion</i>	FirmwareVersion: 20170313.	Firmware version
<i>IsoAreaMaxSize</i>	IsoAreaMaxSize: 0 KB	Maximum size of ISO CD image
<i>DeviceSerialNumber</i>	DeviceSN: EF15EF4016C66250-888F1A4139000000	Unique serial number of the device


If the Device's Serial Number is zero, then there is no guarantee for stable operation of the device.

## 5.2. Termination(*Close*)




*Close* command does nothing.

## 5.3. Fast searching of the device(*UsbInternalCheck*)




The device operates as removable CD drive. If another removable CD drive exists in the system, connection time maybe will be long. To prevent this, *UsbInternalCheck* command is used for fast searching of the device.

## 5.4. CMOS LED control(CmosLed)



When user want to enroll or identify, must send the CmosLed command first.

## 5.5. Changing UART baud rate (*ChangeBaudrate*)




This command changes the UART baud rate at the run-time.


The device initializes its UART baud rate to 9600 bps after power on.




## 5.6. Get enrolled fingerprint count(*GetEnrollCount*)




## 5.7. Check enrollment status(*CheckEnrolled*)




## 5.8. Start an enrollment(*EnrollStart*)




## 5.9. Make 1<sup>st</sup> template for an enrollment(*Enroll1*)



## 5.10. Make 2<sup>nd</sup> template for an enrollment(*Enroll2*)




## 5.11. Make 3<sup>rd</sup> template for an enrollment, merge three templates(*Enroll3*)



To enroll a fingerprint, the host must issue above 4 commands, later chapter describes how to organize these commands.

## 5.12. Check finger pressing status(*IsPressFinger*)




This command is used while enrollment, the host waits to take off the finger per enrollment stage.


### NOTE:

Check the take off finger state can use the *IsPressFinger* command or the touch signal. When the *IsPressFinger* command return parameter is nonzero or the touch signal is low, the finger is taking off the fingerprint sensor.


## 5.13. Delete one fingerprint(*DeleteID*)




## 5.14. Delete all fingerprints(*DeleteAll*)




## 5.15. 1:1 Verification(*Verify*)



## 5.16. 1:N Identification(*Identify*)




## 5.17. 1:1 Verification of Template(*VerifyTemplate*)






## 5.18. 1:N Identification of Template(*IdentifyTemplate*)



## 5.19. Capture fingerprint(*CaptureFinger*)




The fingerprint algorithm uses **450dpi** 256x256 image for its input. This command captures raw image from the sensor and converts it to 256x256 image for the fingerprint algorithm. If the finger is not pressed, this command returns with non-acknowledge. Please use best image for enrollment to get best enrollment data. Please use not best image for identification (verification) to get fast user sensibility.

### NOTE:


Check the finger press on fingerprint sensor must use **the *CaptureFinger* command and Touch signal**. When the *CaptureFinger* command return **ACK** and the touch signal is high, the finger is pressing on fingerprint sensor.

## 5.20. Make Template(*MakeTemplate*)




This function makes template for transmission. *CaptureFinger* command should be previously issued. Do not use the template for registration.


## 5.21. Get fingerprint image(*GetImage*)




## 5.22. Get raw image(*GetRawImage*)




## 5.23. Get template(*GetTemplate*)



## 5.24. Set template(*SetTemplate*)




## 5.25. Start database download, obsolete(*GetDatabaseStart*)




*GetDatabaseStart* command does nothing. It exists for historical reason; it was used for RS232 communication.

## 5.26. End database download, obsolete(*GetDatabaseEnd*)




*GetDatabaseEnd* command does nothing. It exists for historical reason; it was used for RS232 communication.

## 5.27. Set SecurityLevel




## 5.28. GetSecurityLevel






## 5.29. EnterStandbyMode



Enter Standby Mode (Low power mode). If user want the fingerprint module to leave standby mode, please send the 0x00 first and wait 20mS to weak up and then send the standard command.

## 5.30. Identify\_Template2



## 6. Protocol: Flowchart, description

### 6.1. Capture of the fingerprint image

*IsPressFinger* checks whether a finger placed on the sensor. This function is used especially while enrollment.

*CaptureFinger* captures a fingerprint image (256x256), if a finger isn't placed on the sensor, it returns with error.

If this function returns with success, the device's internal RAM keeps valid fingerprint image for the subsequent commands. If the host issues other command, the fingerprint image will be used and destroyed.

*GetRawImage* captures a raw live image (320x240), it doesn't check whether a finger placed on the sensor, this function is used for debug or calibration.

**" *IsPressFinger* & *CaptureFinger* " commnad must correspond with the touch signal (ICPCK) together.**

### 6.2. Identifying and Verifying

*Identify* and *IdentifyTemplate* perform 1: N matching operation.

*Verify* and *VerifyTemplate* perform 1: 1 matching operation.

Just before calling of image-related matching functions (*Identify*, *Verify*), the host must call *CaptureFinger*.

### 6.3. Enrollment

An enrollment flowchart is as below.

1. *EnrollStart* with a (not used) ID
2. *CaptureFinger* & Check ICPCK is "high".
3. *Enroll1*
4. Wait to take off the finger using *IsPressFinger*
5. *CaptureFinger* & Check ICPCK is "high".
6. *Enroll2*
7. Wait to take off the finger using *IsPressFinger*
8. *CaptureFinger* & Check ICPCK is "high".
9. *Enroll3*

